PREPARING FOR YOUR VIRTUAL TRAINING


The ORD training may be taken using *either* Bentley's Imperial configuration that is installed with the software, or if you are a KYTC employee or consultant completing KYTC work, you may use KYTC's configuration. These directions apply to either situation. Steps that are specific to one or the other are noted.

Prior to the class, there are a few things that must be done on your machine.

- For KYTC employees, please email KYTCCaddSupport@ky.gov if you have any problems with these instructions.
- For Consultants, you may need the assistance of your IT department.

Downloads

- 1. You should have **OpenRoads Designer 2021 R1** or **R2** installed on your machine. The book and data files are specifically for these versions of software.
- 2. KYTC: Make certain the current KYTC configuration is installed. Consultants can download it here: <u>https://transportation.ky.gov/cadd-standards/pages/default.aspx</u>
- 3. Download and install the data files for the class.
 - a. Go to the **OpenRoads Designer** download page here: <u>https://www.dropbox.com/s/g0tcpws2prjxuvx/ORD_Training_2023.exe?dl=0</u>
 - b. Select the Download drop-down and then select Direct download.



This downloads a self-extracting zip file. Your file name will be different than the ones shown in the images.



- 4. Double-click the *ORD_Training_2023.exe* from your download folder location.
- 5. If you receive a Windows warning message about an unrecognized app, select **More Info**, then select **Run anyway**.

Windows protected your PC	Windows protected your PC
Microsoft Defender SmartScreen prevented an unrecognized app from starting. Running this app might put your PC at risk. <u>More info</u>	Microsoft Defender SmartScreen prevented an unrecognized app from starting. Running this app might put your PC at risk. App: KYTC_ORD_Training_06_21.exe Publisher: Unknown publisher
Don't run	Run anyway Don't run

6. If you receive any other warning from your virus protection software, select the option to run the program anyway.

The file may be unrecognized, but it is virus-free.

7. From the WinZip Self-Extractor window, verify the Unzip to folder location is C:\ then select **Unzip**.


WinZip Self-Extractor - KYTC_ORD_Training_06_21.exe		
To unzip all files in this self-extractor file to the specified folder press the Unzip button.	Unzip	
Unzip to folder:	Run WinZip	
Browse	Close	
Overwrite files without prompting	About	
	Help	

After unzipping, select **OK**, then **Close** the WinZip Self-Extractor.

Important! Do not specify a location other than C:\ The extraction will create the project folder structure called for in class.



8. Check that you have a C:\Projects\ORD_Training with subfolders for the training class.



Important! If for whatever reason, you cannot or do not install the files in this location, see the README in C:\Projects\ORD_Training for additional information on installing the data.

- KYTC Employees/KYTC Consultants: If your configuration is installed in the KYTC default location of *C:\KYTC_ORD_Standards*, run the *C:\Projects\ORD_Training\KYTC_Config_Class_Setup.bat* file to copy the WorkSet files to the appropriate folder. If your configuration is installed elsewhere, the WorkSet files (.dgnws and .cfg) must be manually copied to the appropriate location from the WorkSet_Files subfolder (check with your IT department if you're unsure).
- 10. Other Consultants: If your Bentley configuration is installed in the default location, run the C:\Projects\ORD_Training\Bentley_Config_Class_Setup.bat file to copy the WorkSet files to the appropriate folder. If your Bentley configuration is installed elsewhere, the WorkSet files (.dgnws and .cfg) must be manually copied to the appropriate location from the WorkSet_Files subfolder (check with your IT department if you're unsure).




Test your setup

- 11. Start ORD
- 12. If you see a **Welcome** page, pick the arrow on the right side to go to the **Work Page** which is shown below.

KYTC Employees/KYTC Consultants:

Other Consultants:



13. Set the 1) Appropriate WorkSpace (either is sufficient, you do not need both) and 2) WorkSet as shown, then 3) **Browse** and 4) **Open** *HWY_60_PI_Locations.dgn*.

KYTC_Standards_WSP is part of the KYTC configuration installation. If you do not see it, the configuration is not installed correctly.

Imperial_Standards is part of the default install of OpenRoads.

ORD_Training is part of the data file installation. If you do not see ORD_Training, you do not have the data installed correctly. **Do not create the WorkSet**, be certain the data files are installed in the correct location and go back to either step 9 or 10 whichever is applicable in your situation.

14. If you receive a WorkSet Alert choose the options to Use active.

Note: If you're using a later version of software, select Yes to upgrade the file.




15. Choose File > Help > About OpenRoads Designer to check the version of software installed. You should have 2021 Release 1 *or 2*. The book is written specifically for these versions.

(ϵ)	C:\Projects\ORD_Training\dgn\HWY_60_PLCocations.dgn [2D - V8 DGN] - OpenRoads Designer CE 2021 Release 1		
New	Help		
Open	Help Contents OpenRoads Designer Help Documentation	About OpenRoads Designer X OpenRoads Designer CE - 2021 Release 1 Jpdate 10	
Save		Version 10.10.01.03	
Save As	Bentley Institute Link to Bentley Institute Training	This product is licensed to: snugent@cadprodinc.com CAD Productivity Inc	
Save Settings Send Mail	Openkoads Designer Community Link to Openkoads Designer Community	Memory Statistics Elemente 633M, 4894 Blocks Available: 53756M (Physical), 134209880M (Virtual)	
Close Tools		Avanaule SJJJohn (Frijskal), 1540300m (virtua) System 65264M (Physica), 134217728M (Virtua)	
Settings Properties		Current File C:\Projects\ORD_Training\dgn\HWY_f60_PLLocations.dgn [2D - V8 DGN]	
Print	RSS Reader Open RSS Reader	Copyright (c) 2020 Bentley Systems, Incorporated. All Rights Reserved. Including software, file formats, and audio-visual displays; may be used pursuant to applicable software license agreement; contains confidential and proprietary information of Bentley Systems	
Import Export	ReadMe Display Product Requirements, Installation Guide and Le	and/or third parties which is protected by copyright and trade secret law and may not be provided or otherwise made available without proper authorization. TRADEMARK NOTICE Bentley, the "8" Bentley logo, and MicroStation are registered or non-registered trademarks of	
Downgrade Civil Model Publish iModel		Bentley Systems, Inc. or Bentley Software, Inc. All other marks are the property of their respective owners.	
Help		Close Legal and Patent Notices System Info	
Feedback			
Exit			

16. **Close**, then back-arrow at the upper left.



17. Choose **Explorer** and expand the categories as shown (this will take a minute).



KYTC Employees / KYTC Consultants:

Other Consultants:

1	Drawing - 🛛 🗸 🖨 🖶 🛃 🕼 🧄 - 🖈 📌 🚍 -
Fi	ile Home View Annotate Attach Analyze Curves Constraints
S	k None ▼ Default ▼ Image: Constraint of the second sec
Front	Attributes Primary
_	lorer
V	Items *
0	Resources
8	OpenRoads Model 😽
P	Sheet Index 🔹
<pre>Pe</pre>	🛚 Links 🔹 👻
	OpenRoads Standards
R	2 🔍 🔊 ::
Se	earch ♀♀ ×
7	Standards
	▲ Md Libraries
L	✓ ✓ Feature Definitions
L	V Reature Definition (Training_Patures_Levels_Element Templates_Annotation)
L	Feature Definition (Drainage and Utilities Features Annotations Imperial.dg
L	Feature Definition (Common Features Annotations Levels Elem Temp Item)
L	Feature Definition (Survey Settings Features Annotations Elem Temp Imper
L	Feature Definition (Site Settings Features Annotations Levels Elem Temp Im
Ν	Feature Definition (Road Features Annotations Levels Elem Temp Imperial.
	Keature Symbologies
	M Annotation Groups
	M Annotation Definitions
	▷ 🚾 Civil Cells
	Design Standards
	▷ M Terrain Filters
	<u>M</u> Survey Settings
	We Ounty Finers ORD_User_Interface.dgn (Default)

- 18. You *must* see these Feature Definition files, although they will differ depending up on your configuration as shown. If you do not, either the configuration or your files are not installed properly. Consult KYTC CADD Support or your IT Department. Without proper installation of the configuration (either KYTC's *or* Bentley's) and the class data files you will not be able to work the class assignments successfully.
- 19. Close ORD after verifying you have the necessary files.



Prepare for Zoom

- 1. Zoom Client should be installed. Please download it here: (https://zoom.us/download).
 - For KYTC employees, if you have trouble downloading from this link, check the Software Center on your machine and try downloading Zoom from there.
- 2. Follow these directions to join a test meeting: <u>https://support.zoom.us/hc/en-us/articles/115002262083-Joining-a-Test-Meeting?mobile_site=true</u>
- 3. You must have an internet connection with enough bandwidth to support video streaming.
- 4. A microphone and speakers (or headset) are required for the best experience.
- 5. A video camera is recommended but not required.

You're ready for training!

You will receive a manual prior to class. We will be using the manual throughout the class, so be sure you have it available each day.

During class, please join from the same machine where your software is loaded – when we go into breakout rooms, you will be sharing your screen with me for questions.

If you are unfamiliar with Zoom and like more detailed information, here's a link to a Zoom video on joining a meeting. <u>https://support.zoom.us/hc/en-us/articles/201362193</u> and don't forget to download the tips sheet on the page where you found this list.